



### 16.2 Soundingram Configuration.



**TAB 1 – Format.**



The Soundingram's configuration options are accessed from the screens' Options menu as shown left.

There are 4 tabs of configuration options. TAB 1 (at left) lets the user select displays using up to four soundings, and displays using one or two diagram panels. These options allow various combinations of data analyses and comparisons.

Using the format options as selected on the example Tab 1, which reflects a two panel display with two soundings, the "Data mode" display option is selected which allows a unique method of data comparison. An example soundingram display is shown below. Here the left panel displays the potential temperature of two soundings while the right panel displays the relative humidity.

